


TMR8SP3ENG



---

## **Install Guide**

**TransMagic R8SP3**

This installation guide will walk you through the steps necessary to download, install and license TransMagic. TransMagic licensing works in one of two different modes; either Stand Alone (your computer only), or as a floating network license. If you are running a Stand Alone license, you will need to request a new license key. In the case of the floating network license, the registration process is handled by your network administrator. Please contact CAMTEX support for assistance if you have purchased a floating network license and need help.

### **Prerequisites**

TransMagic Release 8 Service Pack 3 is officially supported on Windows XP 32bit, Windows Vista 32bit and Windows 7 32bit.

It runs as a 32-bit application on 64-bit versions of XP/VISTA/Win7.

We don't support TransMagic on VISTA home editions.

Microsoft .NET 2.0 Framework, Visual C++ 2005 SP1 and Visual C++ 2008 SP1 run-time libraries are required. If you do not have these libraries installed, you will be prompted to download them from Microsoft's web site. Please follow the instructions provided on Microsoft's web site to complete the installation.

It is required that you log into your computer as a user with Administrator privileges prior to installing TransMagic. Also you have to disable the user access control (UAC) temporarily to install TransMagic.

Also, all previous versions of TransMagic must be un-installed prior to installing R8 SP3.

**IMPORTANT:** Upgrading to R8 SP3 will probably require a new license key. Please be advised that the process of obtaining a new license key is not immediate. License Keys are issued normally within 1 working day.

### **STEP 1 Initialize setup**

Log in with an administrative account.

#### Windows XP

Please start the installation by clicking setup.exe

#### Windows Vista / Windows 7

Please start the installation by right clicking on setup.exe and choose "Run as administrator"

### **STEP 2 Install**

The automated installation wizard will walk you through the following steps:

1. Download and install any required Microsoft components, if necessary.
2. Un-Install previous versions of TransMagic.
3. Install TransMagic R8 SP3.
4. Prompt to install CAD Interface if you have a supported CAD system installed on your computer.

During the installation process you will be prompted to select "Network" or "Stand Alone" installation. This determines where the license key resides. For network installations your IT department may have to setup a license on a server which your TransMagic computer will connect to. If you are not sure you are most likely using a Stand Alone license.

### **STEP 3 Register**

From the Windows Start button select All Programs>TransMagic R8>License Manager then click "Register License Key". This will open the License Key dialog.

1) Select the Reference Code then press Ctrl+C on the keyboard to copy this code to your clipboard.

2) If you have already filled out our online registration form, email the Reference Code directly to

[License@TransMagic.de](mailto:License@TransMagic.de)

If you have not registered before, please click on the "Request License Key" button and fill out the online registration form.

3) When you receive your License Key in a reply email, copy it to your clipboard, open the License Manager and paste the Reference Code in the License Key box.

### **Summary**

At this point you should be ready to start using TransMagic. To get started, we recommend that you read the separate Quick Start Guide.

Please review also the program-internal Help Documentation. There are also new video tutorials located within the tutorial section of the Help Documentation that provide detailed explanations of some of the more advanced capabilities within the product.

CAMTEX GmbH  
Silbergrund 17  
D-98527 SUHL, Germany

Fon +49 (3681) 779-200  
Fax +49 (3681) 779-210

[www.camtex.de](http://www.camtex.de)  
[info@camtex.de](mailto:info@camtex.de)